1 How to use the Astra camera

1 How to use the Astra camera

1.1 SDK usage - Linux

1.1.1 dependent environment

1.1.2 Camera SDK&Samples

1.1.3 OpenNI camera test tool

1.2 AstraSDK-win

1.2.1 Install the driver

1.2.2 Download SDK

1.3 OrbbecViewer-win

1.4 Web monitoring

Official website link: http://www.orbbec.com.cn/

Developer Community: https://developer.orbbec.com.cn/

Astra Camera: https://github.com/orbbec/ros astra camera

Normal camera: https://github.com/bosch-ros-pkg/usb cam.git

Astra SDK: https://developer.orbbec.com.cn/download.html?id=53

Basic use of Astra SDK for Windows: https://developer.orbbec.com.cn/course-details.html?id=53

Astra SDK environment setup: https://developer.orbbec.com.cn/course-details.html?id=16

• Create astra udev rule


In the new environment, you need to execute the [create_udev_rules] file in the [scripts] folder of the [astra_camera] function package, enter the directory where the file is located, and execute the command

./create_udev_rules

launch start command

Launch file	Start the camera model		
astra.launch	Astra, Astra S, Astra mini, Astra mini S		
astraplus.launch	more		
astrapro.launch	Astra pro		
embedded_s.launch	Deeyea		
dabai_u3.launch	Nature		
gemini.launch	Gemini		

Camera hardware structure diagram:



1.1 SDK usage - Linux


Operating environment: virtual machine or dual system

Developer Community: https://developer.orbbec.com.cn/download.html?id=53

1.1.1 dependent environment

sudo apt-get install ros-melodic-serial ros-melodic-bfl ros-melodic-mbf-msgs ros-melodic-pointcloud-to-laserscan ros-melodic-rgbd-launch ros-melodic-libuvc-* ros-melodic-uvc-camera ros-melodic-usb-cam ros-melodic-ar-track-alvar ros-melodic-camera-calibration build-essential freeglut3 freeglut3-dev libsfml-dev

Go to the developer community to download the SDK file, that is(Astra SDK and OpenNI2 SDK, the version and system architecture must match).



Note: All searches on the Internet are for the latest version. The versions in our supporting materials include [v2.1.2], [v2.1.3], etc. The following takes [v2.1.2] as an example, other versions are similar.

1.1.2 Camera SDK&Samples

The folder name and file path may not be the same, change them according to your needs.

```
tar -zxvf AstraSDK-v2.1.2-Ubuntu18.04-x86_64.tar.gz cd AstraSDK-v2.1.2-Ubuntu18.04-x86_64/install # Go to the install folder sudo sh ./install.sh
```

The output contains the following two lines, pay attention to delete the install in the penultimate path:

```
export ASTRA_SDK_INCLUDE=/home/yahboom/software/AstraSDK-v2.1.2-Ubuntu18.04-x86_64/install/include
export ASTRA_SDK_LIB=/home/yahboom/software/AstraSDK-v2.1.2-Ubuntu18.04-x86_64/install/lib
```

After deleting install:

```
export ASTRA_SDK_INCLUDE=/home/yahboom/software/AstraSDK-v2.1.2-Ubuntu18.04-x86_64/include
export ASTRA_SDK_LIB=/home/yahboom/software/AstraSDK-v2.1.2-Ubuntu18.04-x86_64/lib
```

Copy the output to the end of ~/.bashrc

```
gedit ~/.bashrc
source ~/.bashrc
```

The amples directory is the sample program, which needs to depend on the include and lib directories


• SFML effect demo

The bin folder is as follows:

astra-tests				
BodyReaderPoll				
ColorizedBodyViewer-SFML				
ColorReaderEvent				
ColorReaderEventCPP				
ColorReaderPoll				
DebugHandViewer				
DepthReaderEvent				
DepthReaderEventCPP				
DepthReaderPoll				
HandReader				
▲ Inconsolata.otf				
InfraredColorReaderEvent				
InfraredReaderEvent				
InfraredReaderPoll				
MaskedColorViewer-SFML				
MultiSensorViewer-SFML				
RotatedBodyViewer-SFML				
SimpleBodyViewer-SFML				
SimpleColorViewer-SFML				
SimpleDepthViewer-SFML				
SimpleHandViewer-SFML				
SimpleStreamViewer-SFML				

Note: sudo ./ or ./ can be used to start the bin folder, and the files with the suffix -SFML will be displayed on the screen; the methods are similar, and other effects can be tested. If the virtual machine fails to start, please try several times, it is easier to start under the dual system.

```
cd ~/AstraSDK-v2.1.2-Ubuntu18.04-x86_64/bin/
./SimpleBodyViewer-SFML # Skeleton detection
./SimpleHandViewer-SFML # finger following
```



1.1.3 OpenNI camera test tool

Install OpenNI

```
unzip OpenNI_2.3.0.55.zip
cd OpenNI_2.3.0.55/Linux/OpenNI-Linux-x64-2.3.0.55
chmod +x install.sh
sudo ./install.sh
```

the device to initialize the OpenNI environment

```
source OpenNIDevEnvironment
```

compile and run


```
cd Samples/SimpleViewer
make
cd Bin/x64-Release
./SimpleViewer
```




1.2 AstraSDK-win

https://developer.orbbec.com.cn/download.html?id=32


1.2.1 Install the driver




After the download is complete, double-click to install it. The signs of success are as follows




1.2.2 Download SDK



After the download is complete, unzip the folder,




Enter the bin folder and double-click any file with the suffix exe to test it.




1.3 OrbbecViewer-win

https://developer.orbbec.com.cn/download.html?id=77



Unzip, enter the OrbbecViewer_v1.1.1 folder, double-click OrbbecViewer.exe That's it.



1.4 Web monitoring

Environment construction

sudo apt-get install ros-melodic-async-web-server-cpp ros-melodic-web-video-server ros-melodic-usb-cam

Start the camera

```
roslaunch astra_camera astrapro.launch # Astra
roslaunch usb_cam usb_cam-test.launch # USB
```

start web_video_server

```
rosrun web_video_server web_video_server
```

Check

```
View in local web browser
http://localhost:8080/
It must be under the same local area network, and other devices can view it
http://192.168.2.103:8080/
(192.168.2.103 is the IP address of the master)
Note: It is recommended to use Google Chrome or mobile QQ browser, other browsers
may not be able to open the image
```